

Fertilizing scheme PROFESSIONAL (A+B)

All amounts are in ml. per 100 litres of water	Growth period	Week 1	Week 2	Week 3	Week 4	Week 5	Week 6	Week 7	Week 8	Week 9
A+B scheme										
Nutri Forte A+B or Coco Forte A+B	100A + 100B	150A + 150B	175A + 175B	200A + 200B	225A + 225B	200A + 200B	175A + 175B	150A + 150B	< 150A + < 150B	-
P 20	-	25	50	25	-	-	-	-	-	-
K 20	-	-	-	10	25	50	65	80	100	-
BN Roots	add 10ml per litre	-	-	-	add 10ml per litre	-	-	-	-	-
BN X-ceL	50	50	75	75	100	100	100	100	100	100
The Missing Link	50	50	50	50	50	50	50	50	50	50
BN-Zym	30	30	30	30	30	30	30	30	30	30
VitaSol	-	-	-	-	-	50	75	100	125	150

Useful tips for the PROFESSIONAL fertilizing scheme

- First add water to the feed vessel, then add Supermix and stir well.
- In areas of soft water it is recommended to add Ca15 to the Supermixes.
- When using Nutri Forte or Coco Forte, first mix A and then add B.
- For the SuperMixes, add PK 13-14 and mix well (not for Nutri Forte & Coco Forte).
- Leave the mix for one hour and then adjust the pH to pH value 5.8.
- The dosage of the main fertilizer can be adjusted by $\pm 10\%$.
- Do not use fertilizer in the last week before harvest, only water!
- For long flowering plants and when using LongFlower mix, the schedule should be extended, beginning week 4 or 5.
- Triple the amount of Ca 15 when using Reverse Osmosis water (max 100ml /100 l of water).
- VitaSol can be used to improve the taste of the crop. In this case reduce the dosage of main fertilizer by 10 - 25%.
- Spraymix can be applied every week to improve crop vitality.
- Use BN Roots once when planting and repeat after 30 days. In periods of high stress in the plants BN Roots can be used every week.
- Depending on the type of crop, you can adjust the Supermix dosage incrementally, in steps of 10% in accordance with your own insight.
- < indicates the dosage may be adjusted at your discretion.